



Palm Conduit Release Notes For Meeting Maker v8.6

April 9, 2007

GENERAL INFORMATION

- The official release version is Palm Conduits for Meeting Maker v8.6
- This release is composed of the following:
 - Meeting Maker Palm Conduits
- The Meeting Maker client must be installed prior to running the Palm conduit installer.
- You can only use the Palm Conduits for Meeting Maker v8.6 with Meeting Maker v8.6 server. The conduits will not work properly with prior versions.
- Links to download all components can be found in the download section of this document

FEATURE ENHANCEMENTS IN THE PALM CONDUITS FOR MEETING MAKER V8.6

NEW FEATURES IN PALM CONDUITS FOR MEETING MAKER V8.6

Updated Time Zone Definitions

Meeting Maker v8.6.0 has been updated with all of the changes in time zone rules throughout the world. Most notably, the United States has enacted the "Energy Policy Act of 2005" which will change daylight savings time, starting in 2007 on the second Sunday of March to the first Sunday of November. All currently scheduled events that cross one or both of these dates in affected time zones will be adjusted to occur at the correct times.

INSTALLATION INFORMATION

Installing the Palm Desktop Software

To synchronize Meeting Maker to your Palm handheld device install the Palm Desktop software. Refer to the Palm Desktop documentation.

Remember these important facts:

- If you are using a Handspring Visor, you must install the Handspring version of the Palm Desktop software.
- You can download the latest version of the Palm Desktop software for Windows or Macintosh from this site: <http://www.palm.com/support/downloads/>
- If this link does not work, go to <http://www.palm.com> and navigate to the downloads page.
- Once you install the Palm Desktop Software, install Meeting Maker with the Conduits.

Installing Meeting Maker with Conduits

- The 8.6 Meeting Maker conduits for Palm OS handheld devices is a separate installation from the Meeting Maker Calendar installation.
- You must install the Meeting Maker client before you install the Meeting Maker Palm Conduits.
- You must also install the Palm Desktop software before you install the Meeting Maker Palm Conduits
- You should synchronize to the Palm Desktop software first before installing and synchronizing with the Meeting Maker Conduits.

Note: By default, Meeting Maker installs the To Do conduit and the Date Book conduit. If you want to install just the Address Book conduit, or don't want to install the To Do or Date Book conduits, you can change the selected options at installation.

You can configure your synchronization to determine how to synchronize each conduit, or accept the default configuration and immediately synchronize your Meeting Maker data to your Palm device. In some cases, you may need to configure synchronization manually before synchronizing.

KNOWN ISSUES

First Time Meeting Maker Palm Conduit users on the Mac

If you receive the following message on your first sync attempt with the 8.6 Meeting Maker Palm Conduits:

"A conflict in the installed conduits has been detected"

"To allow synchronization to proceed, use the Conduit Settings dialog to turn off the extra conduits for this user, or drag the extra conduits to the Disabled Conduits folder. See the HotSync Log for details"

The hotsync manager recognizes that you have installed additional conduits that perform similar functions of conduits previously installed. To correct:

- Open the Conduit Settings dialog in the Hotsync manager
- Set the "Next HotSync Action" to "Do Nothing" for the previously used address, datebook or task conduits and
- Set the "Do Nothing" action as the default action.
- Alternatively you can move the previously used conduits to a Disabled Conduits folder.

Banners and Palm Devices [6008 & 3761]

If you create multiple banners on the same day on your Palm device, when you synchronize to Meeting Maker, the banners appear in the same row.

You can create banners in Meeting Maker with a duration that is greater than one day. Multi-day banners will only synchronize the first occurrence, because Palm devices do not support multi-day banners. Recurring single-day banners do synchronize. If you want to synchronize a multi-day banner with a Palm device, create it instead as a daily recurring banner.

DOWNLOAD INFORMATION

MEETING MAKER PALM CONDUITS FOR VERSION 8.6

Windows English:

ftp://ftp.meetingmaker.com/support/mm/v860/86_win_palm_conduits.zip

Mac OS X English:

ftp://ftp.meetingmaker.com/support/mm/v860/86_osx_palm_conduits.zip

-End-